



SOFTWARE RELEASE NOTES

MCS-CONFIG **Version 18.01G** **06/01/2018**

Updates from previous versions:

New Features:

1. In ALL cfg types V17 on the MAG INFO screen on the Condenser Info panel on the Control Condenser On: panel adding a radio option called Diff PSI(Disc - Suct).
2. In HVAC and CENT cfg types V17 on the MAG INFO screen on the General Info panel on the Unit Type panel adding a radio option called Heat Recovery. Setting the memory location on ALL cfg types even though the option is not displayed in ALL cfg types.

Bug Fixes:

1. In ALL cfg types V17 on the CIRCUIT BASE screen on the Compressor Grid(1st) the Liquid Injection ON during Fast Unloading is not working correctly, keeps switching back to YES when NO is selected and the file is saved. Resolution: The test for this column is looking at a value that is reset to 255 every time cfg is opened which resets it to Yes for any cfg. Changing test to look at the value of the Liquid Injection column memory location first and if NOT 0 then test the Slide Multiplier memory location for the Starting Compressor circuit that the row is on.

Any questions regarding this release, contact:
support@mcscontrols.com

Micro Control Systems, Inc. 5580 Enterprise Parkway Fort Myers, Florida 33905
(239)694-0089 FAX: (239)694-0031 www.mcscontrols.com

Information contained in this document has been prepared by Micro Control Systems, Inc. and is copyright © protected 2018. Copying or distributing this document is prohibited unless expressly approved by MCS.