



SOFTWARE RELEASE NOTES

MCS-MAGNUM Version 9.13C 04/24/2013

Updates from previous versions:

RTU Only:

New Features:

1. The pre heat function has been added.
 - a. Set point #44, the cent pump down timer has been moved to the safety time in set point #43.
 - b. Set point #170, the excess purge time has been moved to the safety time in set point #169.
 - c. (new definitions for these 2 set points in the pre heat documentation)

Bug Fixes:

1. In a prior release of RTU the night set back cell of set point #220 was used as an adjustment to the condenser cut in (set point #45) and cut out (set point #46) when the unit is in dehumidification mode. **THIS MUST BE CHANGED** to use the night set back cell of set point #45. To make this adjustment the system must be dehumidification mode and this set point must be a Target type.

Any questions regarding this release, contact:
support@mcscontrols.com

Micro Control Systems, Inc. 5580 Enterprise Parkway Fort Myers, Florida 33905
(239)694-0089 FAX: (239)694-0031 www.mcscontrols.com

Information contained in this document has been prepared by Micro Control Systems, Inc. and is copyright © protected 2013. Copying or distributing this document is prohibited unless expressly approved by MCS.